

MAINTENANCE - CLEAR GEL REBALANCE (performed every 3-4 weeks)- AKZENTZ CLASSIC LINE

PREP

- spray each nail with Nail Prep and wipe well with terry towel
- apply cuticle softener (Orly- Cutique) to each cuticle
- using metal cuticle pusher gently remove any non living tissue from the nail plate
- again spray each nail with Nail Prep and wipe with towel
- using electric file (medium sanding band) or hand file (100 grit) shorten the nails.
- using electric file (low speed) cut a smile line following the natural smile line. Remove all the gel from the free edge down to the natural nail.

Next remove about 30% of the remaining gel. Remove pockets or lifted area (if present).

Remove shine from the natural nail.

- dust each nail with a synthetic brush
- with cotton saturated with Nail Prep wipe each nail well (paying attention to sidewalls)
- apply Methacrylic Primer (Primer Pen- MAP) sparingly to exposed natural nail only and let it dry to chalky white surface or apply Affixit (non-acid primer) and let it dry 1 min (doesn't dry to chalky white)

APPLICATION

- with a short oval brush apply small amount of **Bonding gel** to all 10 nails. "Rub" the Bonding gel into the nails. Make sure that gel never touches the skin or floods the sidewalls. The surface of the nails should still look "grainy" and scratched, not glossy. If the nails looks glossy, too much Bonding gel is applied.
- with oval brush apply **Builder Gel** to the free edge. From the side the free edge should be even with the rest of the gel. Repeat on all 10.
- apply **Natural Clear** to the nail bed area paying special attention to rebuilding and re-inforcing the sides of the nails. Brush the gel over the free edge lightly. Cure 2 min.

FINISHING

- with cotton saturated well with Gel Cleanser wipe all 10 nails. The nails and the surrounding skin should never feel "sticky"
- using 100/180 file shape the free edge and the sides.
- using electric file (medium sanding band) perfect the shape of the nail. Remember about proper bit angle.
- with cone bit clean under the nails
- dust nails with synthetic brush
- using white buffing block (180 grit) even out the surface of the gel.
- turn the hand upside down (fingertips towards the ceiling) and shape the free edge (that gives you client's view)
- dust nails with synthetic brush
- with cotton saturated in Akzentz Nail Prep wipe all 10 nails. Make sure that you or the client doesn't touch the nails (** important)
- apply **Top Gloss** to all 10 nails. Use light and even strokes. Cure 2:00- 2:20 min.
- with cotton saturated with Gel Cleanser wipe all 10 nails.
- apply cuticle oil.

Written by Anna Lajourdie for Polished.ca. For personal use only. Please do not copy without permission.