

## RE-GLOSS (aka. Fill) - AKZENTZ CLASSIC LINE

### PREP

- spray each nail with Nail Prep and wipe well with terry towel
- apply cuticle softener (Orly- Cutique) to each cuticle
- using metal cuticle pusher gently remove any non living tissue from the nail plate
- again spray each nail with Nail Prep and wipe with towel
- using electric file (medium sanding band) or hand file (180 grit) remove about 10% of the gel and shape the nail. Remove shine from the natural nail
- turn the hand upside down (fingertips towards the ceiling) and shape the free edge (that gives you client's view)
- remove the dust each nail at a time with a synthetic brush
- with cotton saturated with Nail Prep wipe each nail well (paying attention to sidewalls)
- apply Methacrylic Primer sparingly to exposed natural nail only and let it dry to chalky white surface or Affixit (non acid primer) and let dry for 1 min. Make sure that you or the client doesn't touch the nails (\*\* important)

### APPLICATION & FINISHING

- using light, even strokes apply **Trilite** gel to all 10 nails. Cure 2:00- 2:20 min.
- with cotton saturated with Gel Cleanser wipe all 10 nails.
- apply cuticle oil.

"Re-Gloss" (aka. Fill) could be performed when the nails are still in a perfect condition (about a 1-2 weeks after a full set or a rebalance).

If any free edge separations or lifting is present- perform "rebalance".