

NATURAL NAIL GEL OVERLAY- CLEAR (AKZENTZ CLASSIC LINE)

PREP

- spray each nail with Nail Prep and wipe well with terry towel
- apply cuticle softener (Orly- Cutique) to each cuticle
- using metal cuticle pusher gently remove any non living tissue from the nail plate
- again spray each nail with Nail Prep and wipe with towel (to de-activate cuticle remover)
- remove the shine from the natural nail using electric file (medium sanding band/low speed) or hand file (180 grit)
- dust each nail with a synthetic brush
- with cotton saturated well with Nail Prep wipe each nail (paying attention to sidewalls)
- apply Methacrylic Primer (Primer Pen- MAP) sparingly to each nail and let it dry to chalky white surface or Affixit (acid free primer) and let dry 1 min (Affixit doesn't dry to chalky white- it's normal)

APPLICATION

- with a short oval brush apply small amount of **Bonding gel** to all 10 nails. "Rub" the Bonding gel into the nails. Make sure that gel never touches the skin or floods the sidewalls. The surface of the nails should still look "grainy" and scratched, not glossy. If the nails look glossy, too much Bonding gel is applied.
- with an oval, sable brush apply **Builder gel** to the free edges of all 10 nails. Use light floating movements. Make sure that the surface is as even as possible and free edge are reinforced. Cure 2 min.
- apply **Natural Clear** or Natural Pink from just below cuticle area up to the Builder and brush it lightly over the Builder. Use light floating movement and reinforce the stress and sidewalls. Cure 2 min.

FINISHING

- with cotton saturated well with Gel Cleanser wipe all 10 nails. The nails and the surrounding skin should never feel "sticky"
- using 100/180 file shape the free edge and the sides.
- using electric file (sanding band- medium) shape entire surface of the nail from side to side. Remember about proper angle of the drill bit.
- with cone drill bit clean under the nail.
- dust nails with synthetic brush
- using white buffing block (180 grit) even out the surface of the gel.
- dust nails with synthetic brush
- turn the hand upside down (fingertips towards the ceiling) and shape the free edge (that gives you client's view)
- with cotton saturated in Akzentz Nail Prep wipe all 10 nails. Make sure that you or the client doesn't touch the nails (** important)
- apply **Top Gloss** to all 10 nails. Use light and even strokes. Cure 2:00- 2:20 min.
- with cotton saturated with Gel Cleanser wipe all 10 nails.
- apply cuticle oil.