

## SCULPTING - (NATURAL FREE EDGE)- AKZENTZ CLASSIC LINE

### PREP

- spray each nail with Nail Prep and wipe well with terry towel
- apply cuticle softener (Orly- Cutique) to each cuticle
- using metal cuticle pusher gently remove any non living tissue from the nail plate
- again spray each nail with Nail Prep and wipe with towel (to de-activate cuticle remover)
- remove the shine from the natural nail using electric file (low speed/medium sanding band) or hand file (180 grit)
- dust each nail with a synthetic brush
- with cotton saturated well with Nail Prep wipe each nail (paying attention to sidewalls)
- apply Methacrylic Primer (Primer Pen- MAP) sparingly to each nail and let it dry to chalky white surface or Affixit (acid free primer) and let dry 1 min (Affixit doesn't dry to chalky white- it's normal)

### APPLICATION

- with a short oval brush apply small amount of **Bonding gel** to all 10 nails. "Rub" the Bonding gel into the nails. Make sure that gel never touches the skin or floods the sidewalls. The surface of the nails should still look "grainy" and scratched, not glossy. If the nails look glossy, too much Bonding gel is applied.
- apply form on 1 nail at a time.
- with oval brush apply **French White (natural white)** to create extension (1 nail at a time). Apply the gel on the form first and then push the gel up a little, overlapping the natural nail slightly.
- with oval brush apply **Natural Clear** the cuticle up to the white gel. Use light floating movements. Make sure that the surface is as even as possible and sidewalls and free edge are reinforced. Cure 2 min.
- feather Natural Clear over any low areas if necessary. Cure 2 min.

### FINISHING

- with cotton saturated well with Gel Cleanser wipe all 10 nails. The nails and the surrounding skin should never feel "sticky"
- using 100/180 file shape the free edge and the sides.
- with cone drill bit remove excess of the white gel from under the nail.
- using electric file (medium sanding band) shape entire surface of the nail from side to side. Remember about proper angle of the drill bit.
- dust nails with synthetic brush
- using white buffing block (180 grit) even out the surface of the gel.
- dust nails with synthetic brush
- turn the hand upside down (fingertips towards the ceiling) and shape the free edge (that gives you client's view)
- with cotton saturated in Akzentz Nail Prep wipe all 10 nails. Make sure that you or the client doesn't touch the nails (\*\* important)
- apply **Top Gloss** to all 10 nails. Use light and even strokes. Cure 2:00- 2:20 min.
- with cotton saturated with Gel Cleanser wipe all 10 nails.
- apply cuticle oil.